# Migrate Proline-Zero from a version (N-1) to a newer version(N)

### Structure

Structure of Proline-Zero application, for example version 2.0.1, is as following:

✓ Proline-Zero-2.0.1	^ Nom	Modifié le	Туре	Taille
> 🔒 data	.prolinestudio	15/06/2021 09:33	Dossier de fichiers	
lib	databases	16/11/2021 15:41	Dossier de fichiers	
	🔄 fasta	12/04/2019 15:46	Dossier de fichiers	
> bgsql	mascot	09/11/2021 14:34	Dossier de fichiers	
> PM-SequenceRepository-0.8.0		23/11/2021 10:48	Dossier de fichiers	
> 📙 Proline-Admin-GUI-0.8.1		23/11/2021 10:49	Dossier de fichiers	
> Proline-Cortex-2.0.1				
>				

There are the required modules (PM-SequenceRepository, Proline-Admin, Proline-Cortex, Proline-Studio and postgresl server pgsql) and a folder for preferences, work files and data (projects databases, mascot result files etc...)

#### New installation

Proline-Zero is an all-in-one solution distributed as a zip file. A "new installation" simply involves extracting this zip file and thus creating a new hierarchy ...

Example for version 2.1.2



## Data migration

In order to get back your previous data in a new installation, some copy will be necessary **BEFORE** running the new Proline-Zero. If you have already started the new Proline-Zero see "Specificities" below.

To migrate data, you will have to:

- Copy some files (preferred than a move in a first step in case an error occurs) from directory <Proline-Zero-Version\_N-1>\data to <Proline-Zero-Version\_N>\data
  - Folder ....\data\databases in ....\data\
  - Folders ...\data\fasta and ...\data\mzdb in ...\data

- Files ....\data\mascot\\*.\* in ....\data\mascot\ mascot may contain subfolders which should be copied as well.
- Copy and overwrite file ...\data\.prolinestudio\config\Preferences.properties in ...\data\.prolinestudio\config\
- NOTE: data\tmp folder and other files in data\.prolinestudio\\* should not be copied
- **NOTE**: A graphical interface allows you to set almost all parameters from *proline\_launcher.config*, so it's best to change your settings again through this interface. If you prefer to modify them manually :
  - If you have changed default Proline-Zero configuration you will have to copy these specific parameters from <Proline-Zero-Version\_N>\proline\_launcher.config in new file <Proline-Zero-Version\_N>\proline\_launcher.config
    - You CAN NOT replace new proline\_launcher.config with previous one as modules versions are specified in this file and some parameter names should have been modified.
    - Parameters names which may have change (depending on versions)
      - server\_max\_memory 
         total\_max\_memory
      - postgresql\_port 
         data\_store\_port : should not be changed without
         a good reason ;)
    - New parameters
      - studio\_max\_memory : to specify memory for the GUI application
      - adjust\_memory: should be kept to on (or commented). A new memory management will be available since Proline-Zero 2.2.0
  - Still in <Proline-Zero-Version\_N>\proline\_launcher.config,
    - To force migration of all needed database set parameter "force\_datastore\_update = on" for the first time you will run Proline-Zero. Then this parameter can be set to off again.

## Specificities and warning:

- If you have already run the new Proline-Zero !!
  - In this case, project databases have been initialized. You will need to delete it before copying the previous databases. It is NOT possible to merge databases from two Proline-Zero to keep projects from both installations!
    - Delete (or rename) < Proline-Zero-Version\_N>\data\databases\pg before you copy this folder from the previous version (see above).
- You want to migrate data from **Proline-Zero 2.0.1 (or less) to Proline-Zero 2.1.0 (or higher).** The postgresql server version (pgsql) is not the same. In order to be able to read databases created in Proline 2.0.1 in the new Proline-Zero you will have to use previous postgresql server
  - Rename folder <*Proline-Zero-Version\_N*>\pgsql to <*Proline-Zero-Version\_N*>\pgsql\_9.6

- Copy folder <Proline-Zero-Version\_N-1>\pgsql to <Proline-Zero-Version\_N>\
- You want to migrate data from Proline-Zero 2.1.3 (or less) to Proline-Zero 2.2.0 (or higher).

The Proline-Zero configuration file, *proline\_launcher.config*, is not structured in the same way. The new version of Proline-Zero now displays a GUI for configuration. You will have to report previous values in this display.

🗫 Proline zero co	onfig window				
Modules					
Start Proline Ser	ver				
Start Sequence	Repository				
Start Proline Stu	idio				
Memory Folders	Server Parsing rules				
Men	nory				
Spec	fy the desired memory all	ocation mode and the am	ount of me	mory.	
In Au	tomatic mode, only the To				e memory for
	component. mi-automatic mode, memo	ory amount for Proline Stu	udio can be	specified as well a	is Server
mem	ory to dispatch between o	ther components.			
Final	y, in manual mode, the an	nount of memory for each	h componen	nt should be specif	ied.
Allocation					
Total memory :		12 🔹	Go		
Client					
Proline Studio		2 🔹	Go		
Server					
Server memor	/:	10 🐥	Go		
	Sequence repository :		-	Мо	
	sequence repository :		0 🗘	MO	
	DataStore :		3,2 🌲	Go	
	Proline server :		5,8 🜩	Go	
				_	
	JMS :		1 🔹	Go	
Do not show agai	n				
_ sense show aga					
Bo not show ugu O Restore Sett	·			🖌 Ok	X Cancel

BEFORE RUNNING new Proline-Zero, be sure the application structure is as expected ....

#### Running new version

Once all modifications and copy have been done, you can launch the new version of Proline-Zero. Depending on the previous and new version, a pop-up should appear indicating that an update is necessary. You should click "Do upgrade" in order to be able to launch Proline-Zero.

Proline Zero	×			
"Update Databse Necessary" detected				
Do upgrade No		*		

You should recover your projects and data!